

# Managed enterprises

The **Enterprises** page (*Dashboard* → *Enterprises*) is the control center for managed enterprise access. It lists all enterprises visible to your multi-tenancy account and lets you filter, inspect ownership/delegation, enter an enterprise context, and create new managed enterprises (main accounts only).

## Search and filters

- **Search enterprise:** filters by enterprise name or enterprise ID.
- **Delegation:** **All**, **Delegated**, or **Not delegated**.
- **License status:** **All**, **Valid**, **Expiring**, **Expired**, or **Terminated**.

## Enterprise cards

Each enterprise card shows key management metadata:

- **License status** with icon badge and contextual tooltip.
- **Licensed devices** (enterprise device limit).
- **Next scheduled renewal** or **Expiration date**, depending on subscription state.
- **Delegation** state (**Owner**, **Granted**, or **Not granted**).
- **Owner** display name and username.

## Recently selected enterprises

Enterprises that you accessed recently are pinned to a **Recently selected** section to speed up repeated context switching.

## Enterprise actions

- **Enter enterprise:** opens the selected enterprise context when delegation/ownership allows access.
- **Manage billing:** opens enterprise billing management when available and permitted.
- **Buy license:** opens enterprise purchase flow when billing is not active.

## Who can manage licenses

For enterprises created by a multi-tenancy account, license management is controlled by multi-tenancy users. The main account can always manage billing and license actions for those enterprises.

Sub-accounts can manage billing and license actions only if the main account grants the **Can manage license** permission in the [Sub-accounts](#) page.

# Create managed enterprise

Main multi-tenancy accounts can expand **Create managed enterprise** from the bottom action area.

- **Enterprise name** is required.
- **Create per-enterprise admin user** controls ownership mode.
- When enabled, **Admin username** (email format) and **Admin name** are required.
- Before creation, a confirmation dialog summarizes the operation and, when applicable, warns that temporary credentials are sent by email to the new admin user.

## Ownership mode

- **Per-enterprise admin enabled:** the new admin user owns the enterprise and can delegate management to your multi-tenancy account.
- **Per-enterprise admin disabled:** the enterprise is owned directly by your multi-tenancy account.

## Enterprise quota

If the account reaches the configured enterprise quota, creation is blocked and the form shows a support contact message with current and maximum enterprise count.

When the enterprise quota is reached, you cannot create additional managed enterprises until your limit is increased.

---

Revision #13

Created 2026-02-27 11:59:33 UTC by Admin

Updated 2026-04-22 15:46:40 UTC by Admin