Managed enterprises

The **Enterprises** page (*Dashboard → Enterprises*) is the control center for managed enterprise access. It lists all enterprises visible to your multi-tenancy account and lets you filter, inspect ownership/delegation, enter an enterprise context, and create new managed enterprises (main accounts only).

Search and filters

- **Search enterprise**: filters by enterprise name or enterprise ID.
- **Delegation**: **All**, **Delegated**, or **Not delegated**.
- **License status**: **All**, **Valid**, **Expiring**, **Expired**, or **Terminated**.

Enterprise cards

Each enterprise card shows key management metadata:

- **License status** with icon badge and contextual tooltip.
- **Licensed devices** (enterprise device limit).
- **Next scheduled renewal** or **Expiration date**, depending on subscription state.
- **Delegation** state (**Owner**, **Granted**, or **Not granted**).
- **Owner** display name and username.

Recently selected enterprises

Enterprises that you accessed recently are pinned to a **Recently selected** section to speed up repeated context switching.

Enterprise actions

- **Enter enterprise**: opens the selected enterprise context when delegation/ownership allows access.
- **Manage billing**: opens enterprise billing management when available and permitted.
- **Buy license**: opens enterprise purchase flow when billing is not active.

Who can manage licenses

For enterprises created by a multi-tenancy account, license management is controlled by multi-tenancy users. The main account can always manage billing and license actions for those enterprises.

Sub-accounts can manage billing and license actions only if the main account grants the **Can manage license** permission in the **Sub-accounts** page.

Create managed enterprise

Main multi-tenancy accounts can expand **Create managed enterprise** from the bottom action area.

- **Enterprise name** is required.
- **Create per-enterprise admin user** controls ownership mode.
- When enabled, **Admin username** (email format) and **Admin name** are required.
- Before creation, a confirmation dialog summarizes the operation and, when applicable, warns that temporary credentials are sent by email to the new admin user.

> The new admin user must choose a new password the first time they sign in with the temporary password.

Ownership mode

- **Per-enterprise admin enabled**: the new admin user owns the enterprise and can delegate management to your multi-tenancy account.
- **Per-enterprise admin disabled**: the enterprise is owned directly by your multi-tenancy account.

Enterprise quota

If the account reaches the configured enterprise quota, creation is blocked and the form shows a support contact message with current and maximum enterprise count.

> When the enterprise quota is reached, you cannot create additional managed enterprises until your limit is increased.

Revision #36
Created 2026-02-27 11:59:33 UTC by Admin
Updated 2026-11-12 09:52:02 UTC by Admin