

Kiosk mode

With kiosk mode, you can restrict a device's functionality to a single app or multiple apps. Choosing between single-app and multi-app kiosk mode depends on your business goals.

In **single-app kiosk mode**, a device is configured for a single application and does not allow end-users to access other apps on the device. They also cannot exit the app, making it a dedicated device for that specific app. To enable this mode, specify an app in the [App management](#) section with **Install type** set to **Kiosk**.

In **multi-app kiosk mode**, devices are allowed access to multiple applications. End-users can navigate between multiple apps through a custom launcher. To enable this mode, turn on the **Kiosk custom launcher** option.

When kiosk mode is enabled, you can also configure whether end users can access certain system features, such as system settings and the status bar.

Kiosk custom launcher

Whether the kiosk custom launcher is enabled. This replaces the home screen with a launcher that locks down the device to the apps installed via the [App management](#) setting. Apps appear on a single page in alphabetical order.

Power button actions

Sets the behavior of a device in kiosk mode when a user presses and holds (long-presses) the Power button.

Available (default): The power menu (e.g. Power off, Restart) is shown when a user long-presses the Power button of a device in kiosk mode.

Blocked: The power menu (e.g. Power off, Restart) is not shown when a user long-presses the Power button of a device in kiosk mode. Note: this may prevent users from turning off the device.

System error warnings

Specifies whether system error dialogs for crashed or unresponsive apps are blocked in kiosk mode. When blocked, the system will force-stop the app as if the user chooses the "close app" option on the UI.

Blocked (default): All system error dialogs, such as crash and app not responding (ANR) are blocked. When blocked, the system force-stops the app as if the user closes the app from the UI.

Enabled: All system error dialogs such as crash and app not responding (ANR) are displayed.

System navigation

Specifies which navigation features are enabled (e.g. Home, Overview buttons) in kiosk mode.

Disabled (default): The home and Overview buttons are not accessible.

Home only: Only the home button is enabled.

Enabled: Home and overview buttons are enabled.

Status bar

Specifies whether system info and notifications are disabled in kiosk mode.

Disabled (default): System info and notifications are disabled in kiosk mode.

System only: Only system info is shown on the status bar.

Enabled: System info and notifications are shown on the status bar in kiosk mode. Note: For this policy to take effect, the device's home button must be enabled using `kioskCustomization.systemNavigation`.

Device settings

Specifies whether the Settings app is allowed in kiosk mode.

Allowed (default): Access to the Settings app is allowed in kiosk mode.

Blocked: Access to the Settings app is not allowed in kiosk mode.